

G3 is the next generation protocols for the DMC family of products it:

- Includes additional features*
- Permits future expansion
- Removes critical, device specific parameters, from “field/ customer” access (for data security)
- Supports a high security data integrity checks

The G3 Protocol presently has the following additional features:

- DMC 3000 Display configuration options permits choice of additional display content and order of presentation
- A “Semi-Latching” dose rate alarm (rate alarm will latch for 10 seconds)
- The dose rate is recorded at each “dose increment” in the histogram
- Enhanced histogram. On an alarm, more histogram data points are available before and after and alarm event regardless of the histogram interval selected.